

WIRELESS INTERNET ACCESS INSTRUCTIONS

To be able to use the wireless network, you must first have either an 802.11b or 802.11g wireless network card installed in your computer. Please contact Information Technology at (618) 985-3741 Ext. 8212 if you need assistance with wireless network card specifications.

Please follow these instructions to connect your computer to the wireless network:

Configuration of your wireless network card:

For Windows XP users:

1. Click *Start*, *Settings*, and *Control Panel*, and then select *Network Connections*.
2. Right-click Wireless Network Connection, and then click Properties.
3. In the Wireless Network Connection Properties dialog box, click on Wireless Network tab and click Add.
4. In the Wireless Network Properties dialog box, enter Network name (SSID) as **JALC Wireless** then click OK.
5. In the Wireless Network Connection Properties dialog box, click OK.

For Windows 2000/98 users:

1. Click Start, point to Settings, click on Control Panel, and then double-click Network.
2. In the Network dialog box, click Add.
3. Click Client, and then click Add. A list of client software appears.
4. In the Manufacturers list, click the name of the manufacturer of your network software.
5. In the Network Clients list, select the client software you are using, and then click OK. The client software is added to your computer.
6. On the Configuration tab, select your client, and then click Properties.
7. Enter Network name (SSID) as **JALC Wireless** then click OK.
8. Click OK, and then click OK again.

Frequently Asked Questions (FAQ):

Q. Where can I access the wireless network?

A. The wireless network can currently be accessed on the JALC main campus.

Q. Is there a printer available to students on the wireless network?

A. Wireless printing is now available. You can print from just about anywhere on campus and pick up your printouts at the Library Circulation Desk for 10 cents per page.

To set up wireless printing on your Windows XP laptop:

- 1) Click on the **Start** Button.
- 2) Click on "Printers and Faxes" (on right hand side of Start Menu).
- 3) Click "Add Printer" (top of left hand menu).
- 4) Click **Next**.
- 5) *Select* "Local printer attached to this computer."
- 6) *Deselect* "Automatically detect and install my Plug and Play printer."
- 7) Click **Next**.

- 8) *Select* "Create a new port" and *select* "Standard TCP/IP Port" from the drop down menu.
- 9) Click **Next**.
- 10) Click **Next**.
- 11) Type "192.168.225.7" in the "Printer Name or IP Address" field.
- 12) Click **Next**.
- 13) Click **Finish**.
- 14) *Select* "HP" from left hand box and "HP LaserJet 2200 Series PCL" from the right hand box.
- 15) Click **Next**.
- 16) *Select* "Yes" or "No" depending if you want this to be your default printer.
- 17) Click **Next**.
- 18) *Select* "No" under "Do you want to print a test page?"
- 19) Click **Next**.
- 20) Click **Finish**.
- 21) *Right click* on "HP LaserJet 2200 Series PCL" In the Printers and Faxes window.
- 22) Click on "Properties."
- 23) Click on the "Advanced" tab.
- 24) Click on **Separator Page**.
- 25) Click on the **Browse** button.
- 26) *Double click* on the last file "sysprtj.sep" and click **OK**.
- 27) Click **OK**.